

Math 4997-1

Lecture 8: Introduction to bond-based peridynamics

<https://www.cct.lsu.edu/~pdiehl/teaching/2020/4997/>

This work is licensed under a Creative Commons "Attribution-NonCommercial-NoDerivatives 4.0 International" license.



Reminder

Classical continuum mechanics

Peridynamics

Discretization

Material models

Implementation

Summary

Reminder

Lecture 8

What you should know from last lecture

- Lambda functions
- Asynchronous programming

Notes

Notes

Notes

Notes

Classical continuum mechanics




Figure: The continuum in the reference configuration Ω_0 and after the deformation $\phi : \Omega_0 \rightarrow \mathbb{R}^3$ with $\det(\text{grad } \phi) > 0$ in the current configuration $\Omega(t)$ at time t .

Prerequisites

- ▶ A material point in the continuum is identified with its position $X \in \mathbb{R}^3$ in the so-called reference configuration $\Omega_0 \subset \mathbb{R}^3$.
- ▶ The reference configuration Ω_0 refers to the shape of the continuum at rest with no internal forces.

Prerequisites

- ▶ The deformation $\phi : [0, T] \times \mathbb{R}^3 \rightarrow \mathbb{R}^3$ of a material point X in the reference configuration Ω_0 to the so-called current configuration $\Omega(t)$ is given by

$$\phi(t, X) := id(X) + u(t, X) = x(t, X)$$

- ▶ where $u : [0, T] \times \mathbb{R}^3 \rightarrow \mathbb{R}^3$ refers to the displacement

$$u(t, X) := x(t, X) - X.$$

- ▶ The stretch $s : [0, T] \times \mathbb{R}^3 \times \mathbb{R}^3 \rightarrow \mathbb{R}^3$ between the material point X and the material point X' after the deformation ϕ in the configuration $\Omega(t)$ is defined by

$$s(t, X, X') := \phi(t, X') - \phi(t, X).$$

Notice

We just covered the prerequisites of classical continuum mechanics which are necessary to introduce the peridynamic theory. For more details, we refer to

- ▶ Liu, I-Shih. Continuum mechanics. Springer Science & Business Media, 2013.
- ▶ Gurtin, Morton E. An introduction to continuum mechanics. Vol. 158. Academic press, 1982.

Notes

Peridynamics

What is peridynamics

- ▶ A non-local generalization of continuum mechanics
- ▶ Has a focus on discontinuous displacement as they arise in fracture mechanics.
- ▶ Models crack and fractures on a mesoscopic scale using Newton's second law (force equals mass times acceleration)

$$F = m \cdot a = m \cdot \ddot{X}$$

- ▶ Silling, Stewart A. "Reformulation of elasticity theory for discontinuities and long-range forces." Journal of the Mechanics and Physics of Solids 48.1 (2000): 175-209.
- ▶ Silling, Stewart A., and Ebrahim Askari. "A meshfree method based on the peridynamic model of solid mechanics." Computers & structures 83.17-18 (2005): 1526-1535.

Notes

Principle I




Figure: The continuum in the reference configuration Ω_0 and the interaction zone $B_\delta(X)$ for material point X with the horizon δ .

Notes

Principle II

Acceleration $a : [0, T] \times \mathbb{R}^3 \rightarrow \mathbb{R}^3$
of a material point at position X at time t is given by

$$\rho(X)a(t,X) := \int_{B_\delta(X)} f\left(t,x(t,X')-x(t,X),X'-X\right)dX'+b(t,X),$$

where $f : [0, T] \times \mathbb{R}^3 \times \mathbb{R}^3 \rightarrow \mathbb{R}^3$ denotes a pair-wise force function, $\rho(X)$ is the mass density and $b : [0, T] \times \mathbb{R}^3 \rightarrow \mathbb{R}^3$ the external force.

Notes

Notes

- [illegible]

Notes

[illegible]

Notes

[illegible]

Notes

- [illegible]

Note that we computed the acceleration of a material point $a(t, X)$ and we need to compute the displacement $u(t, X)$ by a

Central difference scheme

$$u(t+1, X) = 2u(t, X) - u(t-1, X) + \Delta t^2 \left(\sum_{X_j \in B_\delta(X_i)} f(t, X_i, X_j) + b(t, X) \right)$$

to compute the actual displacement $x(t, X) := id(X) + u(t, X)$.

Material models

Prototype Microelastic Brittle (PMB) model

In this model the assumption is made that the pair-wise force f only depends on the relative normalized bond stretch

$$s : [0, T] \times \mathbb{R}^3 \times \mathbb{R}^3 \rightarrow \mathbb{R}$$

$$s(t, x(t, X') - x(t, X), X' - X) := \frac{\|x(t, X') - x(t, X)\| - \|X' - X\|}{\|X' - X\|}.$$

where

- ▶ $X' - X$ is the vector between the material points in the reference configuration,
- ▶ $x(t, X') - x(t, X)$ is the vector between the material point in the current configuration.

Pair-wise bond force f

$$f(t, x(t, X') - x(t, X), X' - X) := c s(t, x(t, X') - x(t, X), X' - X) \frac{x(t, X') - x(t, X)}{\|x(t, X') - x(t, X)\|}$$

with a material dependent stiffness constant c .

More details:

- ▶ Silling, Stewart A., and Ebrahim Askari. "A meshfree method based on the peridynamic model of solid mechanics." Computers & structures 83.17-18 (2005): 1526-1535.
- ▶ Parks, Michael L., et al. "Implementing peridynamics within a molecular dynamics code." Computer Physics Communications 179.11 (2008): 777-783.




Figure: Sketch of the pair-wise linear valued force function f with the stiffness constant c as slope.

Note that there is no notion of failure/damage in the current material model.

Introducing failure

Introduce a scalar valued history dependent function $\mu : [0, T] \times \mathbb{R}^3 \times \mathbb{R}^3 \rightarrow \mathbb{N}$ to the computation of the pair-wise force

$$\begin{aligned} f(t, x(t, X') - x(t, X), X' - X) &:= \\ c s(t, x(t, X') - x(t, X), X' - X) & \\ \mu(t, x(t, X') - x(t, X), X' - X) \frac{x(t, X') - x(t, X)}{\|x(t, X') - x(t, X)\|} &. \end{aligned}$$

with

$$\begin{aligned} \mu(t, x(t, X') - x(t, X), X' - X) &:= & (1) \\ \begin{cases} 1 & s(t, x(t, X') - x(t, X), X' - X) < s_c \\ 0 & \text{otherwise} \end{cases} & & (2) \end{aligned}$$




Figure: Sketch of the pair-wise linear valued force function f with the stiffness constant c as slope and the critical bond stretch s_c .

Definition of damage

With the scalar valued history dependent function μ the notion of damage $d(t, X) : [0, T] \times \mathbb{R}^3 \rightarrow \mathbb{R}$ can be introduced via

$$d(t, X) := 1 - \frac{\int_{B_\delta(X)} \mu(t, x(t, X') - x(t, X), X' - X) dX'}{\int_{B_\delta(X)} dX'} .$$

To express damage in words, it is the ratio of the active (non-broken) bonds and the amount of bonds in the reference configuration within the neighborhood.

Notes

Notes

Notes

Notes

Relation to classical continuum mechanics

Stiffness constant

c = 18K / (pi delta)

Critical bond stretch

s_c = sqrt(5G / (9K delta))

With

- ▶ K is the bulk modulus
- ▶ G is the energy release rat

Notice

We just covered the basics of peridynamics which are necessary to implement peridyannmics for the course project. Fore more details we refer to

- ▶ Bobaru, Florin, et al., eds. Handbook of peridynamic modeling. CRC press, 2016.
- ▶ Madenci E, Oterkus E. Peridynamic Theory. InPeridynamic Theory and Its Applications 2014 (pp. 19-43). Springer, New York, NY.

Implementation

Algorithm

1. Read the input files
2. Compute the neighborhoods B_delta
3. While t_n <= T
 - 3.1 Update the boundary conditions
 - 3.2 Compute the pair-wise forces f
 - 3.3 Compute the acceleration a
 - 3.4 Approximate the displacement
 - 3.5 Compute the new positions
 - 3.6 Output the simulation data
 - 3.7 Update the time step t_n = t_n + 1
 - 3.8 Update the time t = Delta t * t_n

Notes

Notes

Notes

Notes

Summary

Notes

Summary

After this lecture, you should know

- ▶ Concept of peridynamics
- ▶ Discretization of peridynamics
- ▶ Material models

Note that this lecture is not relevant for the exams, but you should understand the content to implement the course project.

Notes

Disclaimer

Some of the material, *e.g.* figures, plots, equations, and sentences, were adapted from P. Diehl, Modeling and Simulation of cracks and fractures with peridynamics in brittle materials, Doktorarbeit, University of Bonn, 2017.

Notes

Notes
